


Register& Update for CR6011, 7001, 7001F, 8001, 8011, 8021, 9081


Take CR7001 for example:

Follow the steps described as below to perform the registration and update:

1. Go to the launch website: mycar.x431.com and click Products, it will jump to new page as bellow.



2. Hover the mouse over “product”. There have five options. Please click “Online Product”. Then find CR7001.





CR123



Creader 9081



Creader 8001



Creader 7001

3. Click CR7001, find “tool download”. You will find “download”. Click it to download the updating tool.

431 Home Products News Video Center Data Center Service & Support About Launch Partner User Account

Creader 7001 Description Feature Specification Relevant Product Tool download

1
 is a multipurpose CReader with color display. It contains 7 diagnostic functions. Each product provides one or multiple of the functions to meet different requirements: OBD reset, BMS reset, SAS reset, DPF bleeding reset. Function style of CR7001 diagnostic functions:

Function
OBD+Engine Oil Lamp Reset
OBD+Oil+EPB+SAS+BMS+DPF+ABS BLEEDING

Buy from **AllExpress** Buy from **Amazon**


Creader 7001	Description	Feature	S
--------------	-------------	---------	---




4. Download and install the Update Tools and launch the program when installed. You will be prompted to type in the Serial Number(located at the back of the device)



5. After the S/N is entered, click **Device Upgrade** and enter the following information (e-mail address and register code), click **Submit**.



- a) The Register Code can be found when you connect the device to your computer via USB cable.
- b) When the device has powered up, place the cursor on the Help > Tool information.





6. Please take the TF card out to the card reader and insert into the computer.


7. Reopen the CR update suite; fill in your user password, click OK.(Note: User password is the Register Code)




8. Select the updates you'd like to perform or click Select ALL and click Download. (Caution: Do not disconnect USB while downloading.)



9. Once the updates are finished, it will pop up the following bar and click OK.



10. Once all steps are completed, please repower up the device via USB in computer. Then click OK to start updating. It may take a while to finish the update. The device will display as below:



11. Now the registration and upgrading process is completed and you can enjoy the updated software.

Note: Please make sure the card reader is removed safely.